

XML

```
<soapenv:Envelope>
  <soapenv:Body>
    <soapenv:Fault>
      <faultcode>Server</faultcode>
      <faultstring>Description of the server fault</faultstring> DDQ-ERROR-MESSAGE
    </soapenv:Fault>
  </soapenv:Body>
</soapenv:Envelope>
```

COBOL copybook

05	DDQ-OUTPUT-MESSAGE.	
faultstring	10	DDQ-ERROR-MESSAGE PIC X(80).
	10	DDQ-CAVEAT-TEXT PIC X(67) OCCURS 3 TIMES.
	10	DDQ-RESPONSE-DATA OCCURS 5 TIMES.
	15	DDQ-PERSON.
	20	DDQ-DOB PIC X(10).
	20	DDQ-EYES PIC X(03).
	20	DDQ-HAIR PIC X(03).
	20	DDQ-HEIGHT PIC X(03).
	20	DDQ-HEIGHT-TEXT PIC X(55).
	20	DDQ-FIRST-NAME PIC X(15).
	20	DDQ-MIDDLE-NAME PIC X(15).
	20	DDQ-LAST-NAME PIC X(25).
	20	DDQ-SUFFIX PIC X(04).
	20	DDQ-DONOR-INDICATOR PIC X(05).
	20	DDQ-SEX PIC X(01).
	20	DDQ-SSN PIC X(04).
	20	DDQ-WEIGHT PIC X(03).
	20	DDQ-WEIGHT-TEXT PIC X(03).
	20	DDQ-AKA-DOB PIC X(10).
	20	DDQ-AKA-NAME PIC X(59).
	15	DDQ-ADDRESS.
	20	DDQ-STREET PIC X(40).
	20	DDQ-CITY PIC X(13).
	20	DDQ-STATE PIC X(02).
	20	DDQ-ZIP PIC X(05).
	15	DDQ-LICENSE.
	20	DDQ-PIN PIC X(09).
	20	DDQ-DRIVER-LICTYPE-DESC PIC X(30).
	20	DDQ-JURISDICTION PIC X(02).
	20	DDQ-ENDORSEMENT OCCURS 6 TIMES.
	25	DDQ-ENDORSEMENT-CODE PIC X(01).
	25	DDQ-ENDORSEMENT-DESC PIC X(19).
	20	DDQ-EXPIRATION-DATE PIC X(10).
	20	DDQ-ISSUE-DATE PIC X(10).
	20	DDQ-RESTRICTIONS OCCURS 5 TIMES.
	25	DDQ-RESTRICTION-CODE PIC X(01).
	25	DDQ-RESTRICTION-DESC PIC X(24).
	20	DDQ-CDL-CLASS-CODE PIC X(01).
	20	DDQ-CDL-STATUS-CODE PIC X(30).
	20	DDQ-DRIVER-STATUS-CODE PIC X(30).